



Palace Command Summary

The following table provides a list of all special commands (not counting Iptscrae commands and keywords):

- *Guest commands* on page 55
- *Member commands* on page 56
- *Operator commands* on page 57
- *Owner commands* on page 59

Guest commands

The following table lists the Palace guest commands.

| Guest Commands | Syntax | Description |
|-----------------------|----------------------|---|
| help | 'help | Displays all special commands available to your user class, in the Log window |
| page | 'page <i>message</i> | Summons help from an operator |
| sitepage | 'sitepage | Displays the URL of this Palace's Site page. |

Member commands

The following table lists the Palace member commands.

| Member Commands | Syntax | Description |
|-----------------|---|--|
| hide | 'hide on 'hide off | Hides you from all other users Unhides you from all other users |
| hidefrom | 'hidefrom <i>name</i> | Hides you from user <i>name</i> |
| mute | `mute <i>name</i> | Mutes user <i>name</i> |
| newroom | 'newroom 'newroom [<i>roomName</i>] | Creates your member room (one per user) Creates your member room as <i>roomName</i> |
| page | 'page <i>message</i> | Summons help from an operator |
| password | 'password <i>password</i> | Specifies a password for navigation purposes |
| rclose | 'rclose | Closes your member room to further visitors |
| rdelete | 'rdelete | Deletes your member room |
| re respond | 're <i>message</i> 'respond <i>message</i> | Replies to the last sender of an ESP message |
| rejectesp | 'rejectesp on 'rejectesp off | Rejects all incoming ESP messages Stops rejecting ESP messages |
| rejectprivate | 'rejectprivate on 'rejectprivate off | Rejects all incoming private messages Stop rejecting private messages |
| rguests | 'rguests on 'rguests off | Allows guests to enter your member room Prohibits guests from entering your member room |
| rhide | 'rhide on 'rhide off | Hides your member room from the Room List Unhides your member room from the Room List |
| rkick | 'rkick <i>name</i> | Kicks <i>name</i> out of your member room |
| rname | 'rname <i>roomName</i> | Renames your member room as <i>roomName</i> |
| ropen | 'ropen | Opens your member room to visitors |
| rowner | 'rowner <i>name</i> | Transfers ownership of your member room to user <i>name</i> |
| rpainting | 'rpainting on 'rpainting off | Enables painting in your member room Disables painting in your member room |
| rpassword | 'rpassword [<i>password</i>] | Password-protects your member room |
| rpicture | 'rpicture <i>filename</i> | Sets new background for your member room |



| Member Commands | Syntax | Description |
|-----------------|-------------------------------|---|
| rscripts | 'rscripts on 'rscripts off | Enables scripts in your member room Disables scripts in your member room |
| runhide | 'runhide | Same as `rhide off |
| runkick | 'runkick <i>name</i> | Cancels an `rkick command |
| unhide | 'unhide | Same as `hide off |
| unhidefrom | 'unhidefrom <i>name</i> | Unhides you from user <i>name</i> |
| unmute | 'unmute <i>name</i> | Unmutes user <i>name</i> |

Operator commands

The following table lists the Palace operator commands.

| Operator Commands | Syntax | Description |
|-------------------|--|--|
| autoannounce | 'autoannounce <i>message</i> | Sets the server greeting to <i>message</i> |
| banip | 'banip [<i>minutes</i>] <i>ipAddress</i> | Bans one or more IP addresses for <i>minutes</i> . May use wildcards (i.e.: 12.24.23*). |
| banlist | 'banlist [-k] [-a] [<i>name</i>] <i>ipAddress</i> | Shows banned users in log window |
| banuser | 'banuser [<i>minutes</i>] <i>name</i> | Bans user <i>name</i> for <i>minutes</i> |
| bots | 'bots on 'bots off | Turn user scripts on server-wide Turn user scripts off server-wide |
| comment | 'comment <i>ipAddress</i> <i>message</i> | Adds a comment to a banlist |
| death | 'death <i>minutes</i> | Set default death penalty to <i>minutes</i> |
| delete | 'delete | Deletes the current room |
| duplicate | 'duplicate | Duplicates the current room |
| er | 'er | Moves you to the room of the last (non-operator) page |
| extend | 'extend <i>string minutes</i> | Extends the death penalty on a ban record |
| flood | 'flood <i>number</i> | Kill flooders after <i>number</i> events per second |
| flushprops | 'flushprops <i>n</i> | Clears old props older than <i>n</i> days and compresses the prop file. |

| Operator Commands | Syntax | Description |
|--------------------|---|---|
| gag | 'gag <i>name</i> | Gags user <i>name</i> |
| glist | 'glist [-k -o -p -wl] | Lists information on all users <ul style="list-style-type: none"> • -k Show the users' reg key hash • -o Show the users' software origination code and machine type • -p Show the users' PUID hash • -w List only operators |
| kill | 'kill [<i>minutes</i>] <i>name</i> | Kills (disconnects) user <i>name</i> for <i>minutes</i> |
| list | 'list [-k -o -p -w] [<i>name</i>] <i>ipAddress</i> | Lists information on specific user matching name or IP address <ul style="list-style-type: none"> • -k Show the users' reg key hash • -o Show the users' software origination code and machine type • -p Show the users' PUID hash • -w List only operators |
| operatorcount | 'operatorcount | Displays the number of operators currently logged in. |
| paint | 'paint on 'paint off | Turns painting on server-wide Turns painting off server-wide |
| pin | 'pin <i>name</i> | Pins user <i>name</i> |
| poundprotect | 'poundprotect on off | Enables/ disables pound protection. This logs the IP address of a user who repeatedly makes new connections in a short time interval.) |
| poundcheckinterval | 'poundcheckinterval <i>n</i> | Sets the pound check interval to <i>n</i> seconds. |
| propgag | 'propgag <i>name</i> | Propgags member <i>name</i> |
| purgebanlist | 'purgebanlist | Purges elapsed ban records |
| purgeprops | 'purgeprops <i>number</i> | Purges all props older than <i>number</i> days |
| repage | 'repage <i>message</i> | Sends <i>message</i> to the last (non-operator) page |
| roommaxguests | 'roommaxguests <i>number</i> | Sets the max guest occupancy for the current room |
| roommaxocc | 'roommaxocc <i>number</i> | Sets the max occupancy for the current room |
| savesessionkeys | 'savesessionkeys on 'savesessionkeys off | Enables/ disables saving sessions keys (that is, logs users' ID and reg code to the server log). |
| track | 'track [<i>minutes</i>] <i>name</i> | Tracks all sign-ons from user <i>name</i> for <i>minutes</i> |
| trackip | 'trackip [<i>minutes</i>] <i>ipAddress</i> | Tracks all sign-ons from <i>ipAddress</i> . May use wildcards (i.e.: 12.24.23.*). |
| unban | 'unban <i>name</i> 'unban <i>ipAddress</i> | Unbans user <i>name</i> Unbans user from <i>ipAddress</i> |
| ungag | 'ungag <i>name</i> | Ungags user <i>name</i> |
| unpin | 'unpin <i>name</i> | Unpins user <i>name</i> |

| Operator Commands | Syntax | Description |
|-------------------|---|--|
| unpropgag | 'unpropgag <i>name</i> | Unpropgags member <i>name</i> |
| untrack | 'untrack <i>name</i> 'untrack <i>ipAddress</i> | Stops tracking user <i>name</i> Stops tracking user from <i>ipAddress</i> |

Owner commands

The following table lists the Palace owner commands.

| Owner Commands | Syntax | Description |
|-------------------------------|--|--|
| allowedoperators ¹ | 'allowedoperators on 'allowedoperators off | Enables support for operators Disables support for operators |
| allowedurls | 'allowedurls on 'allowedurls off 'allowedurls " <i>URL</i> " | Enables the allowed URLs string. Enables the allowed URLs string Sets the allowed URLs string or strings (separated by a pipe ()). |
| authoring | 'authoring on 'authoring off | Allows operators to enter Authoring Mode Prevents operators from entering Authoring Mode |
| avatarurl | 'avatarurl on 'avatarurl off 'avatarurl " <i>URL</i> " | Sets custom avatars on. Turns custom avatars off. Sets the avatar directory to the designated URL. |
| ban | 'ban <i>name</i> | Permanently banishes <i>name</i> from the server |
| botkill | 'botkill on 'botkill off | Allows cyborg scripts to kill Prevents cyborg scripts from killing |
| chatlog | 'chatlog on 'chatlog off [<i>filename</i>] | Enables chat logging on the server Disables chat logging on the server |
| custom | 'custom on 'custom off | Enables custom props on the server Disables custom props on the server |
| defaultroomocc | 'defaultroomocc <i>number</i> | Sets the default room occupancy |
| downlist | 'downlist <i>number</i> | Moves the current room <i>number</i> positions down in the script file |
| dropzone | 'dropzone | Makes the current room a dropzone (front gate) |

| Owner Commands | Syntax | Description |
|------------------|--|--|
| entrypage | 'entrypage ["URL"] | Sets the Palace's default entrypage URL for the Palace Directory. If keyword FORCETPVWEBPAGE is set, it's also the entry page for web clients coming in from a non-authorized URL (TPALLOWEDURLS keyword). |
| fileserver | 'fileserver ["URL"] | Sets the location of your media for web-based users. |
| guests | 'guests on 'guests off | Enables guest access to the server Prevents guest access to the server |
| killprop | 'killprop | Removes the prop you are wearing from the server prop file. |
| maxocc | 'maxocc <i>number</i> | Sets the maximum server occupancy |
| memberrooms | 'memberrooms on 'memberrooms off | Allows members to create member rooms Prohibits creation of member rooms |
| nowhisper | 'nowhisper on 'nowhisper off | Disables whispering Enables whispering |
| operatorskill | 'operatorskill on 'operatorskill off | Allows operators to kill Prohibits killing by operators |
| operatoronly | 'operatoronly on 'operatoronly off | Sets the current room as operator only Removes operator-only setting |
| operatorpass | 'operatorpass <i>password</i> | Sets the operator password to <i>password</i> |
| ownerpass | 'ownerpass <i>password</i> | Sets the owner password to <i>password</i> |
| passwordsecurity | 'passwordsecurity | Enables password security (auto-kills after three failed password attempts) |
| picdir | 'picdir <i>path</i> | Sets the source directory for outbound files to <i>path</i> |
| pinprop | 'pinprop 'pinprop on 'pinprop off | Sets the pin prop to the prop you are wearing Turns pin propping on Turns pin propping off |
| playerkill | 'playerkill on 'playerkill off | Allows members to kill Prohibits killing by members |
| propcontrol | 'propcontrol on 'propcontrol off 'propcontrol <i>userlevel</i> | Turns on prop control (only owners can introduce new props) Turns off prop control Lets only <i>userlevel</i> users introduce new props |
| purgelimit | 'purge <i>number</i> 'purgelimit <i>number</i> | Sets the purge limit to <i>number</i> days Same as 'purge <i>number</i> |
| recycle | 'recycle [<i>number</i>] | Causes guest ID numbers to recycle at <i>number</i> |
| reportprefs | 'reportprefs | Lists the current Palace preferences. |



| Owner Commands | Syntax | Description |
|------------------|--|---|
| reset | 'reset | Recomputes all rooms' occupancy count. |
| revision | 'revision | Displays the Palace server version number. |
| roomsfile | 'roomsfile 'roomsfile <i>.patfilename</i> | Shows current file setting Causes your Palace to use the template associated with the named configuration file. This changes the look and feel of your Palace. |
| securejavaaccess | 'securejavaaccess on 'securejavaaccess off | If this is on, additional authorization is required for web-based users. |
| securelogoff | 'securelogoff on off | If this is on, the authentication engine tracks logoffs |
| securesite | 'securesite on off | If this is on, a name and password are required to access this Palace server. |
| security | 'security <i>authhost:[authport]</i> [<i>retrys</i>] off | Sets the security (authentication) daemon. <ul style="list-style-type: none"> • <i>authhost</i> is the daemon's URL • <i>authpot</i> is the daemon's port • <i>retrys</i> specifies how many attempts a user can make. The default is 1. |
| setrank | 'setrank <i>command</i> <i>setting</i> | Sets the rank of the command to the specified setting. |
| servername | 'servername <i>string</i> | Sets the servername to <i>string</i> |
| showranks | 'showranks | Displays each Palace command and its current rank. Modifications via 'setrank are shown in paranthesis. |
| shutdown | 'shutdown | Shuts down the server |
| spooft | 'spooft on 'spooft off | Allows members to spoof using @x,y commands Prohibits spoofing |
| uplist | 'uplist <i>number</i> | Moves the current room <i>number</i> positions up in the script file |

1. Be careful in using this command. If you turn this off, and then log off, you will not be able to access the operator interface again later to turn it on/ off. You will need to use the `~susr ownerpassword` command to get back into owner mode.